

# Register FieldType

- 1 Introduction
- 2 Service container configuration
  - 2.1 Basic configuration
  - 2.2 Legacy Storage Engine
    - 2.2.1 Converter
    - 2.2.2 External storage
    - 2.2.3 Gateway based storage

## Introduction

This document explains how to [register](#) a custom FieldType in eZ Publish 5. It will [not](#) contain the development part as it is already covered in the [API](#) section.

Please be sure you first have read the [basic documentation](#) on how to develop a custom FieldType.

## Service container configuration

To be able to declare a FieldType, you need to have [registered a bundle](#) in your application kernel.

This bundle needs to expose some configuration for the service container somehow (read [related Symfony documentation](#))

## Basic configuration

This part relates to the [base FieldType](#) class that interacts with the Publish API.

Let's take a basic example from [ezstring](#) configuration.

```
parameters:
    ezpublish.fieldType.ezstring.class: eZ\Publish\Core\FieldType\TextLine\Type

services:
    ezpublish.fieldType.ezstring:
        class: %ezpublish.fieldType.ezstring.class%
        parent: ezpublish.fieldType
        tags:
            - {name: ezpublish.fieldType, alias: ezstring}
```

So far, this is a regular service configuration but 2 parts worth particular attention.

- parent

As described in the [Symfony Dependency Injection Component](#) documentation, the `parent` config key indicates that you want your service to inherit from the parent's dependencies, including constructor arguments and method calls. This is actually a helper avoiding repetition in your field type configuration and keeping consistency between all field types.

- tags

Tagging your field type service with `ezpublish.fieldType` is mandatory to be recognized by the API loader as a regular field type, the `alias` key being simply the *fieldTypeIdentifier* (formerly called *datatype string*)

Basic field types configuration is located in `EzPublishCoreBundle/Resources/config/fieldtypes.yml`.

# Legacy Storage Engine

## Converter

As stated in [Field Type API & best practices](#), a conversion of Field Type values is needed in order to properly store the data into the *old* database schema (aka *Legacy Storage*).

Those converters also need to be correctly exposed as services.

### Field Type converter for ezstring

```
parameters:
  ezpublish.fieldType.ezstring.converter.class:
  eZ\Publish\Core\Persistence\Legacy\Content\FieldValue\Converter\TextLine

services:
  ezpublish.fieldType.ezstring.converter:
    class: %ezpublish.fieldType.ezstring.converter.class%
    tags:
      - {name: ezpublish.storageEngine.legacy.converter, alias: ezstring, lazy:
true, callback: '::create'}
```

Here again we need to tag our converter service, with `ezpublish.storageEngine.legacy.converter` tag this time.

As for the tag attributes:

| Attribute name | Usage   |
|----------------|---|
| alias          | Represents the <i>fieldTypeIdentifier</i> (just like for the FieldType service)   |
| lazy           | Boolean indicating if the converter should be lazy loaded or not.<br>Performance wise, it is recommended to set it to <b>true</b> unless you have very specific reasons.  |
| callback       | If lazy is set to true, it represents the callback that will be called to build the converter. <i>Any valid callback can be used.</i><br>Note that if the callback is defined in the converter class, the class name can be omitted.<br>This way, in the example above, the full callback will be resolved to <code>eZ\Publish\Core\Persistence\Legacy\Content\FieldValue\Converter\TextLine::create</code> |

The converter configuration for basic field types are located in [EzPublishCoreBundle/Resources/config/storage\\_engines.yml](#).

## External storage

A FieldType has the ability to store its value (or part of it) in external data sources. This is made possible through the `eZ\Publish\SPI\FieldType\FieldTypeStorage` interface. Thus, if one wants to use this functionality, he needs to define a service implementing this interface and tagged as `ezpublish.fieldType.externalStorageHandler` to be recognized by the Repository.

Here is an example for `ezurl` field type:

## External storage handler for ezurl

```
parameters:
  ezpublish.fieldType.ezurl.externalStorage.class:
  eZ\Publish\Core\FieldType\Url\UrlStorage

services:
  ezpublish.fieldType.ezurl.externalStorage:
    class: %ezpublish.fieldType.ezurl.externalStorage.class%
    tags:
      - {name: ezpublish.fieldType.externalStorageHandler, alias: ezurl}
```

The configuration is straight forward. Nothing specific except the `ezpublish.fieldType.externalStorageHandler` tag, the `alias` attribute still begin the `fieldTypeIdentifier`.

External storage configuration for basic field types is located in `EzPublishCoreBundle/Resources/config/fieldtypes.yml`.

## Gateway based storage

As stated in the [FieldType best practices](#), in order to be storage agnostic and external storage handler should use a *storage gateway*. This can be done by implementing another service implementing `eZ\Publish\Core\FieldType\StorageGateway` and being tagged as `ezpublish.fieldType.externalStorageHandler.gateway`.

## Storage gateway for ezurl

```
parameters:
  ezpublish.fieldType.ezurl.storage_gateway.class:
  eZ\Publish\Core\FieldType\Url\UrlStorage\Gateway\LegacyStorage

services:
  ezpublish.fieldType.ezurl.storage_gateway:
    class: %ezpublish.fieldType.ezurl.storage_gateway.class%
    tags:
      - {name: ezpublish.fieldType.externalStorageHandler.gateway, alias: ezurl,
        identifier: LegacyStorage}
```

| Attribute name | Usage  |
|----------------|--|
| alias          | Represents the <i>fieldTypeIdentifier</i> (just like for the FieldType service)  |
| identifier     | Identifier for the gateway.<br>Must be unique per storage engine. <i>LegacyStorage</i> is the convention name for Legacy Storage Engine. |

For this to work properly, your storage handler must inherit from `eZ\Publish\Core\FieldType\GatewayBasedStorage`.

Also note that there can be several gateways per field type (one per storage engine basically).

The gateway configuration for basic field types are located in `EzPublishCoreBundle/Resources/config/storage_engines.yml`.